# Chapter 3 Adding Assets

# **Chapter Overview**

In this chapter the student will explore all the ways of adding assets. Asset Management stores two types of asset information: financial and physical. Financial information includes cost, books, depreciation method and convention, life, and so on. Physical information includes such things as tag number, specifications, location, custodian, and manufacturer. How your asset receiving is set up will determine what type and how much information you enter when the asset is added.

Asset Management gives you two ways to add assets online. You can use Express Add – add them using asset profiles to default book and depreciation information. This approach is quick and efficient; you enter only the most critical information, and assets are automatically capitalized. Basic Add is the other way to add assets online. It enables you to enter and adjust assets with the maximum amount of both financial and physical detail.

Please note that because of details in the full functionality the preferred method for adding assets is to use Basic Add.

# **Chapter Objectives**


By the end of this lesson, you will be able to:

- Describe the A, B, C, and D tables used in PeopleSoft Asset Management
- Add assets using Express Add
- Add assets using Basic Add (Asset Basic Information)
- · Copy Assets
- Update an Asset's Physical Attributes
- Use the Asset Search Utility

# **Describing the A, B, C, and D Tables**

This diagram depicts the flow of an asset transaction through PeopleSoft Asset Management:

# Asset Management Process Flow



AMD05

**ENTAP Training** 

The Asset Transaction Flow diagram was introduced in the Product Overview lesson. Now the user is ready to add assets on-line to create open transactions that will populate the AM Transaction Tables.

Open transactions include adds, adjustments, recategorizations, retirements, and transfers (both inter and intra unit), as well as the monthly depreciation entries.

The A, B, C, and D tables in PeopleSoft Asset Management store the critical asset information.

When an asset is added to your Asset Management system the following four databases are updated.

Component	Table	Navigation to View	Description
Asset Basic Information	<b>A</b> sset	Asset Management, Owned Assets, Basic Add	Physical information (non-financial) such as Description, Custodian, Location & Tag Number
Asset Book Definition	<b>B</b> ook	Asset Management, Owned Assets, Asset Book Information, Define Depr Criteria	Depreciation Rules, such as Method, Life, In Service Date, Convention
Asset Cost Adjust/ Transfer	<b>C</b> ost	Asset Management, Financial Transactions, Cost Adjust/Transfer, Asset	Financial information such as Cost, Quantity, ChartFields, Category
Asset Depreciation	<b>D</b> epreciation	Asset Management, Review Cost/Depr Activity, Asset Depreciation	Results of depreciation such as Accumulated Depreciation and Depreciation Adjustments

Any activity to the tables above (A, B, or C) creates Open Transactions. Running Depreciation (AMDPCALC) updates the table shown below (D):

# AMT01

Exclusively for use by the State of Indiana

Issue Date: 11/28/2007

Exclusively for use by the State of Indiana


ENTAP Training

# **State of Indiana Policy**

The State of Indiana requires three additional fields for all assets \$500 and over and at the time of receiving. These are Tag Number, Location and Custodian. Other primary fields include Asset Profile, Asset Type, Asset Category, Description, Acquisition Date and Amount. Let's discuss these first three below.

1) Tag Number: This Agency specific field is numeric. The first three fields in the Tag Number are derived from the Agency Unit ID. Note that PeopleSoft calls the Agency ID a Business Unit. Therefore, the Auditor of State (AOS) which has the Agency ID of 00050 will have tag numbers that begin with 050, the last three characters of the Agency ID. Tag Number: These are six (6) numeric digits corresponding to the bar code tag number affixed to the asset. Do not include the first three numbers of the bar code tag number if this is your agency number. If your tag number after your agency number is only five digits, then add a zero to the beginning of the tag number to make it six.

Tags may be purchased through Label Tech, 1100 East Seymour St., Muncie, IN 47302. Phone: (765) 747-1234 or 1-800-359-2155.



AMSC20

2) Custodian: The custodian is the person that guards or protects an asset. For an automobile, this person would be the primary driver of the vehicle. While there could be multiple choices of custodians for a building. When possible, select the custodian from the EMPLID table. If not available, the standard PeopleSoft naming convention will be listed as Last name, First name. There is no space between the names. There are no initials in between the two names. PeopleSoft allows multiple custodians on the same effective date. Please note that if the custodian is unknown at the time of receiving, then the Asset Manager needs to be used as a temporary custodian.



AMSC21

ENTAP Training

Exclusively for use by the State of Indiana
Issue Date: 11/28/2007

Exclusively for use by the State of Indiana
Issue Date: 11/28/2007

ENTAP Training

3) Location: A seven (7) digit alpha numeric field that tells the location of the asset. The location is agency defined it can be room numbers, buildings, part of an address, etc. This is a required field for all adds and retirements. The first three characters of the location represent the Agency ID. Each asset may have multiple locations on the same effective date. Please note that if the proper Asset Location does not exist, GMIS must be contacted to add the proper details into PeopleSoft.



AMSC22

# **State of Indiana Policy**

# 8.2 Internal Control

Agency personnel are responsible for accountability for all assets under their control, including capital assets. Adequate asset management staff should be assigned to recording and maintaining, on the ENCOMPASS financial system, a complete list of all capital assets with a cost greater than \$500. Controls should be in effect to assure that additions, disposals, and transfers to other departments or agencies are recorded timely. Inventories of these assets should be performed each year in each department and compared to the ENCOMPASS listing. Results of inventories should be retained for audit purposes.

Capital assets with a cost \$500 or less may be included in ENCOMPASS Asset Management at the agency's option.

# 8.2.1 Financial Reporting – State CAFR

The State Comprehensive Annual Financial Report (CAFR) is compiled and audited each fiscal year. This report is vital to the State's bond rating and must be prepared in accordance with generally accepted accounting principles (GAAP), which requires capital assets to be included at cost (or estimated cost) and depreciated over the useful life of the asset. In order to obtain this financial information, each agency must maintain certain required information in the asset module of ENCOMPASS.

# 8.2.1.1 What are capital assets?

As defined in GASB 34, capital assets include all of the following, assuming a useful life of greater than one year:

- Land (including right of way, easements)
- Improvements to Land
- Infrastructure (roadways, bridges, etc.)
- Buildings
- Improvements Other than Buildings
- Transportation Equipment
- Machinery and Other Equipment
- Construction in Progress

# 8.2.1.2 Capital Asset Policy

The capital asset policy for Indiana State Government, which includes details of capitalization and depreciation, is maintained by the Auditor of State and can be found in this chapter, Appendix 8.5.1 or at www.in.gov/aos.

# **Asset Profiles**

Listed below is a currentlisting of all Asset Profiles used by the State of Indiana.

	101 LAND				
10101 Land 10102 Right of Way					
151 IMPROVEMENT TO LAND					
15101 Well	15105 Water System`	15109 Utility – Gas			
15102 Septic System	15106 Streets	15110 Utility - Water			
15103 Sewer System	15107 Sidewalks/Curbs	15199 Misc Imprv. to Land			
15104 Landscaping	15108 Utility – Electrical				
	161 ANTIQUES				
16101Antiques/ Inexhaustible ollec.					
	301 BUILDINGS				
30101 Building Office	30116 Education	30131 Fire Station			
30102 Garage	30117 Kitchen/Dining/Laundry	30132 Gate House			
30103 Storage (Other Than Salt)	30118 Power House	30133 Barber Shop			
30104 Lab Test Building	30119 Water/Sewage Plant	30134 Farm Buildings			
30105 Shop	30120 Greenhouse	30135 Bakery			
30106 Weigh Station Building	30121 Armory	30136 Mill (Feed or Saw)			
30107 Rest Area Building	3012 Bath House	30137 Pump House			
30108 Gas House	30123 Concession	30138 Paint Shed (Coal)			
30109 Salt Storage	30124 Fish Hatchery	30140 Lab Test Building			
30110 Unit Building	30125 Historical Building	30142 Refrigeration Building			
30111 Hospital (Infirmary)	30126 Hotel, Motel, Inn	30143 Coal Bunker			
30112 Residential	30127 Apartment House	30144 Multi-Purpose Building			
30113 Dorms/Cottages	30128 Warehouse	30145 Incinerator Building			
30114 Recreation	30129 Cell House	30199 Miscellaneous Building			
30115 Chapel	30130 Industrial Complex				
	351 IMPROVEMENTS TO BUILDING	S			
35101 Doors and Windows	35110 Painting	35118 Coal Conveyor			
35103 Roof/Waterproofing	35111 Land Washing Facility	35119 Insulation			
35104 Air Conditioning, Heating	35112 Boiler Replacement	35120 Imprv Water/Sewage			
35105 New Wings, Rooms	35113 Pool	35122 Fire Alarm System			
35106 Remodeling	35114 Elevator	35123 Septic System			
35107 Electrical	35115 Fire Escape	35124 Air Handling Unit			
35108 Exterior Lighting	35116 WaterTemp, Regulator	35125 Bell System			
35109 VentSys- Kitchen,BoilerRoom	35117 Repair Coal Bunker	35126 Flight Deck			
		35199 Misc.Imprv to Bldg`			

Exclusively for use by the State of Indiana

Issue Date: 11/28/2007

Exclusively for use by the State of Indiana

Exclusively for use by the State of Indiana

ENTAP Training

**ENTAP Training** 

40101 Water Tower	40112 Shelter, Picnic	40123 Amphitheater
40102 Wall & Perimeter Structure	40113 Pool	40124 Bridge
40103 Tunnel	40114 Radio Tower	40125 Boat House
40104 Sewage Dump Station	40115 Sewage Lift Station	40126 MobileHome(Stat./ Mobile)
40106 Boat Dock	40116 Ball Court or Field	40127 Statutes
40107 Control, Entry Gate	40117 Fence	40129 Fish Ladders
40108 Garage, Residential	40118 Fishing Pier	40130 Hatchery Ponds
40109 Diving Platform	40119 Toilet	40131 Fish Cleaning Stations
40110 Fire Tower	40121 Shooting Shelter	40199 Salt Storage Racks
40111 Barn	40122 Ramps	
	402 DOCKS	
40201 Dock – Dolphins	40202 Dock – Fenders	40203 Pier/Dock
	403 HARBORS	
40301 Harbors		
	404 IMPROVEMENTS TO HARBORS	
40401 Harbor Fill Materials	40402 Harbor Protective Coating	40403 Harbor RipRap
	405 & 406 HARBOR MOORING CELL	
40501 Harbor Mooring Cell	40601 Harbor Mooring Cell Impro	vement
451 IMPRO\	/EMENTS TO STRUCTURES OTHER THA	AN BUILDINGS
45101 Painting	45107 New Additions	45113 Fire Alarm Systems
45102 VentSys-Kitchen,BoilerRm	45108 Electrical	45114 Water Treatment
45103 Irrigation System	45109 Exterior Lighting	45115 Aggregate/Paved Surface
45104 Sidewalks & Steps	45110 Fencing, Security	
45106 New Roof	45111 Septic System	
	501 OFFICE EQUIPMENT	
50104 Calculators	50115 Shredder	50128 Laminator
50105 Cash Register	50116 Tape Recorder	50129 Telecopier
50106 Check Writing Machine	50117 Typewriter	50132 Employee Lockers
50107 Copy Machine	50120 Date/Time Stamp	50133 Intercom System
50108 Dictating, Transcribing		FOADE The Challer
Equip	50121 Copy Machine Counter	50135 Time Clock – Key
Equip 50109 Fans	50121 Copy Machine Counter  50122 Electric Letter Opener	50136 Bulletin Board
		,
50109 Fans 50110 Mail Processing	50122 Electric Letter Opener	50136 Bulletin Board
50109 Fans 50110 Mail Processing Equipment	50122 Electric Letter Opener 50124 Binding Machine	50136 Bulletin Board 50150 Hole Punch
50109 Fans 50110 Mail Processing Equipment 50111 Paper Cutter	50122 Electric Letter Opener 50124 Binding Machine 50125 Word Processor	50136 Bulletin Board 50150 Hole Punch 50151 Car Phone

401 STRUCTURES OTHER THAN BUILDINGS

	HOUSEHOLD, KITCHEN, AND LAUN	
50201 Beds	50222 Ironers	50254 Carts
50202 Chairs	50223 Extractor – Water	50256 Kettle
50203 Dehumidifier	50224 Floor Scrubber	50258 Drink Dispenser
50204 Dishwasher Equipment	50226 Ice Maker	50259 Boiler
50205 Disposal	50227 Potato Peeler Machine	50261 Hood (Canopy)
50206 Food Slicer	50229 Kitchen Steamer	50262 Kitchen Units
50207 Freezer	50230 Waxer Buffer	50264 Stove (Wood)
50208 Heaters	50231 Water Softener	50266 Meat Grinder, Hobart
50209 Humidifier	50234 Popcorn Machine	50267 Kitchen Cabinet
50210 Incinerator	50235 Electric Cutters	50270 Folder
50211 Mixer or Small Appliances	50236 Hot Cart	50272 Dry Cleaning Equipment
50213 Oven (All Types)	50237 Grill	50273 Household Cleaners
50214 Range	50241 Coffee & Tea Maker	50274 Laundry Equipment
50215 Refrigerator	50243 Scales	50280 Griddle
50216 Tables	50247 Toaster	50281 Microwave
50217 Tables Dining	50249 Sink	50283 Serving Pans
50218 Television	50250 Large Appl (French Fryer)	50285 Vat
50219 Vacuum Cleaners	50251 Food Warmer	50286 Shelving
50220 Washers	50252 Steam Units	50299 Misc Household, Kitchen
50221 Dryers	50253 Fry Saver	
	503 OFFICE FURNITURE	
50301 Bookcases	50310 Credenza	50319 Shelving Unit
50302 Chairs	50311 Shelf	50320 Podium
50304 Desks	50312 Sofa	50323 Wall Partition
50305 Files	50314 Modular Work Station	50325 Cart
50307 Storage Cabinet	50316 Carpet	50326 Bulletin
50308 Table50308 Table	50318 Lektriever	50399 Misc Office Furniture
	505 AUTOMOBILES	
50501 Automobiles	50502 Pursuit Device	
	506 STA WAGON/CARRY ALLS	
50601 Auto	50604 Twelve Passenger	50607 Ambulance
50602 Bus	50605 Vans	
50603 Four Wheel Drive	50606 Carry All	
	507 PICK UP TRUCKS	
50701 1/2 Ton Truck	50702 Truck with Cab	50703 Pickup Truck Cap

Exclusively for use by the State of Indiana

Issue Date: 11/28/2007

Exclusively for use by the State of Indiana

Issue Date: 11/28/2007

ENTAP Training

50802 1 Ton Pick Up	50801 3/4 Ton Pick Up	50805 Other				
S0804 1 Ton Flat Bed	50802 1 Ton Pick Up	50808 1 1/2 Ton				
S090   Self Propelled   50904   Highway Grader   50903   Grader Blade   50905   Agricultural Grader   510   MOWERS   51001   Brush Cutter   51005   Trimmer   51010   Leaf Blower   51002   Edger   51008   Other Attachments   51004   Rider   51009   Mower   511   TRANSPORTATION EQUIP   51101   ATV   51107   Battery Operated Trucks   51199   Misc Transportation   Equip   51105   Tucker Sno-Cat Groom   51109   Flail   51105   Tucker Sno-Cat Groom   51109   Flail   51106   Trailer   51110   Striping Machine   51203   Snow Blowers   51203   Snow Blade   51203   Snow Blowers   51203   Snow Blowers   51203   Snow Blowers   51204   Snow Plow/Equip   513   CONSTRUCTION AND ENGINEERING EQUIPMENT   51301   Anvil   51310   Backhoe   51319   Planner Used for Lumber   51303   Crane   51311   Transit   51321   Excavator   51302   Earthmover   51312   Bulldozer   51322   Warning Signs   51305   Fork Lift   51313   Other Equip Attachment   51323   Pay Loader   51316   Fornt End Loader   51314   Cement Equipment   51324   Stump Cutters   51307   Post Hole Digger   51315   Distance Measure   51329   MiscConstruct/Engineer   51308   Scaffold   51317   Plotter Stereo   51318   Trencher   51418   BullcDING AND PLANT   51401   Alarm System   51411   Emergency Lights   51424   De-Aerator   51425   Water Softener   51404   Fork Lift   51413   Air Compressor   51431   Ventilation Systems   51405   Furnace   51416   Water Pump   51420   Sewage Grinder   51439   Shelving   51409   Transformer   51421   Conveyors   51442   Hydraulic Sewage Cleaner   51409   Transformer   51421   Conveyors   51442   Hydraulic Sewage Cleaner   51400   Transformer   51421   Conveyors   51442   Hydraulic Sewage Cleaner   51400   Transformer   51421   Conveyors   51442   Hydraulic Sewage Cleaner   51400   Transformer   51421   Conveyors   51442   Hydraulic Sewage Cleaner   51440   Hydraul	50803 1 Ton Dump	50809 Truck Refrigeration Unit				
	50804 1 Ton Flat Bed	50810 Semi Trailer/Tractor				
S1001 Brush Cutter		509 GRADERS				
S100   Brush Cutter	50902 Self Propelled	50904 Highway Grader				
S1001 Brush Cutter	50903 Grader Blade	50905 Agricultural Grader				
S1002 Edger   S1008 Other Attachments		510 MOWERS				
S1004 Rider	51001 Brush Cutter	51005 Trimmer	51010 Leaf Blower			
511 TRANSPORTATION EQUIP           51101 ATV         51107 Battery Operated Trucks         51199 Misc Transportation Equip           51105 Tucker Sno-Cat Groom         51109 Flail         51106 Trailer         51110 Striping Machine           512 SNOW PLOWS AND SCRAPERS           51201 Snow Plow         51203 Snow Blade         51209 Misc Snow Plow/Equip           513 CONSTRUCTION AND ENGINEERING EQUIPMENT           51301 Anvil         51310 Backhoe         51319 Planner Used for Lumber           51303 Crane         51311 Transit         51321 Excavator           51304 Earthmover         51312 Bulldozer         51322 Warning Signs           51305 Fork Lift         51313 Other Equip Attachment         51323 Pay Loader           51305 Fork Lift         51313 Other Equip Attachment         51324 Stump Cutters           51306 Front End Loader         51314 Cement Equipment         51324 Stump Cutters           51307 Post Hole Digger         51315 Distance Measure         51399 MiscConstruct/Engineer           51308 Scaffold         51317 Plotter Stereo         51399 MiscConstruct/Engineer           51309 Tractor         51318 Trencher         51424 De-Aerator           51401 Alarm System         51411 Emergency Lights         51424 De-Aerator           51402 Central Air Conditioner         51412 Boiler	51002 Edger	51008 Other Attachments				
51101 ATV         51107 Battery Operated Trucks         51199 Misc Transportation Equip           51105 Tucker Sno-Cat Groom         51109 Flail           51106 Trailer         51110 Striping Machine           512 SNOW PLOWS AND SCRAPERS           51201 Snow Plow         51203 Snow Blade           51202 Snow Blowers         51299 Misc Snow Plow/Equip           513 CONSTRUCTION AND ENGINEERING EQUIPMENT           51301 Anvil         51310 Backhoe         51319 Planner Used for Lumber           51303 Crane         51311 Transit         51321 Excavator           51304 Earthmover         51312 Bulldozer         51322 Warning Signs           51305 Fork Lift         51313 Other Equip Attachment         51323 Pay Loader           51306 Front End Loader         51314 Cement Equipment         51324 Stump Cutters           51307 Post Hole Digger         51315 Distance Measure         51399 MiscConstruct/Engineer           51308 Scaffold         51317 Plotter Stereo         51399 MiscConstruct/Engineer           51401 Alarm System         51411 Emergency Lights         51424 De-Aerator           51402 Central Air Conditioner         51412 Boiler         51425 Water Softener           51405 Furnace         51416 Water Pump         51432 Regulator           51406 Generator         51417 Air Lift	51004 Rider	51009 Mower				
Equip		511 TRANSPORTATION EQUIP				
51106 Trailer         51110 Striping Machine           51201 Snow Plow         51203 Snow Blade           51202 Snow Blowers         51299 Misc Snow Plow/Equip           513 CONSTRUCTION AND ENGINEERING EQUIPMENT           51301 Anvil         51310 Backhoe         51319 Planner Used for Lumber           51303 Crane         51311 Transit         51321 Excavator           51304 Earthmover         51312 Bulldozer         51322 Warning Signs           51305 Fork Lift         51313 Other Equip Attachment         51323 Pay Loader           51306 Front End Loader         51314 Cement Equipment         51324 Stump Cutters           51307 Post Hole Digger         51315 Distance Measure         51399 MiscConstruct/Engineer           51308 Scaffold         51317 Plotter Stereo         51318 Trencher           51401 Alarm System         51411 Emergency Lights         51424 De-Aerator           51402 Central Air Conditioner         51412 Boiler         51425 Water Softener           51404 Fork Lift         51413 Air Compressor         51431 Ventilation Systems           51405 Furnace         51416 Water Pump         51432 Regulator           51406 Generator         51417 Air Lift         51438 Chemical Tank           51407 Pump         51420 Sewage Grinder         51424 Hydraulic Sewage Cle	51101 ATV	51107 Battery Operated Trucks				
512 SNOW PLOWS AND SCRAPERS           51201 Snow Plow         51203 Snow Blade           51202 Snow Blowers         51299 Misc Snow Plow/Equip           5130 CONSTRUCTION AND ENGINEERING EQUIPMENT           51301 Anvil         51310 Backhoe         51319 Planner Used for Lumber           51303 Crane         51311 Transit         51321 Excavator           51304 Earthmover         51312 Bulldozer         51322 Warning Signs           51305 Fork Lift         51313 Other Equip Attachment         51323 Pay Loader           51306 Front End Loader         51314 Cement Equipment         51324 Stump Cutters           51307 Post Hole Digger         51315 Distance Measure         51399 MiscConstruct/Engineer           51308 Scaffold         51317 Plotter Stereo         51399 MiscConstruct/Engineer           51309 Tractor         51318 Trencher         514 BUILDING AND PLANT           51401 Alarm System         51411 Emergency Lights         51424 De-Aerator           51402 Central Air Conditioner         51412 Boiler         51425 Water Softener           51404 Fork Lift         51413 Air Compressor         51431 Ventilation Systems           51405 Furnace         51416 Water Pump         51432 Regulator           51406 Generator         51417 Air Lift         51438 Chemical Tank           51407	51105 Tucker Sno-Cat Groom	51109 Flail				
51201 Snow Plow         51203 Snow Blade           51202 Snow Blowers         51299 Misc Snow Plow/Equip           513 CONSTRUCTION AND ENGINEERING EQUIPMENT           51301 Anvil         51310 Backhoe         51319 Planner Used for Lumber           51303 Crane         51311 Transit         51321 Excavator           51304 Earthmover         51312 Bulldozer         51322 Warning Signs           51305 Fork Lift         51313 Other Equip Attachment         51323 Pay Loader           51306 Front End Loader         51314 Cement Equipment         51324 Stump Cutters           51307 Post Hole Digger         51315 Distance Measure         51399 MiscConstruct/Engineer           51308 Scaffold         51317 Plotter Stereo         51399 MiscConstruct/Engineer           51309 Tractor         51318 Trencher         5148 BUILDING AND PLANT           51401 Alarm System         51411 Emergency Lights         51424 De-Aerator           51402 Central Air Conditioner         51412 Boiler         51425 Water Softener           51404 Fork Lift         51413 Air Compressor         51431 Ventilation Systems           51405 Furnace         51416 Water Pump         51432 Regulator           51406 Generator         51417 Air Lift         51438 Chemical Tank           51407 Pump         51420 Sewage Grinder         51442 Hydraulic	51106 Trailer	51110 Striping Machine				
51202 Snow Blowers         51299 Misc Snow Plow/Equip           513 CONSTRUCTION AND ENGINEERING EQUIPMENT           51301 Anvil         51310 Backhoe         51319 Planner Used for Lumber           51303 Crane         51311 Transit         51321 Excavator           51304 Earthmover         51312 Bulldozer         51322 Warning Signs           51305 Fork Lift         51313 Other Equip Attachment         51323 Pay Loader           51306 Front End Loader         51314 Cement Equipment         51324 Stump Cutters           51307 Post Hole Digger         51315 Distance Measure         51399 MiscConstruct/Engineer           51308 Scaffold         51317 Plotter Stereo         51318 Trencher           51309 Tractor         51318 Trencher         51424 De-Aerator           51401 Alarm System         51411 Emergency Lights         51424 De-Aerator           51402 Central Air Conditioner         51412 Boiler         51425 Water Softener           51404 Fork Lift         51413 Air Compressor         51431 Ventilation Systems           51405 Furnace         51416 Water Pump         51432 Regulator           51406 Generator         51417 Air Lift         51438 Chemical Tank           51407 Pump         51420 Sewage Grinder         51442 Hydraulic Sewage Cleaner		512 SNOW PLOWS AND SCRAPERS				
513 CONSTRUCTION AND ENGINEERING EQUIPMENT           51301 Anvil         51310 Backhoe         51319 Planner Used for Lumber           51303 Crane         51311 Transit         51321 Excavator           51304 Earthmover         51312 Bulldozer         51322 Warning Signs           51305 Fork Lift         51313 Other Equip Attachment         51323 Pay Loader           51306 Front End Loader         51314 Cement Equipment         51324 Stump Cutters           51307 Post Hole Digger         51315 Distance Measure         51399 MiscConstruct/Engineer           51308 Scaffold         51317 Plotter Stereo           51309 Tractor         51318 Trencher           514 BUILDING AND PLANT           51401 Alarm System         51411 Emergency Lights         51424 De-Aerator           51402 Central Air Conditioner         51412 Boiler         51425 Water Softener           51404 Fork Lift         51413 Air Compressor         51431 Ventilation Systems           51405 Furnace         51416 Water Pump         51432 Regulator           51406 Generator         51417 Air Lift         51438 Chemical Tank           51407 Pump         51420 Sewage Grinder         51439 Shelving           51409 Transformer         51421 Conveyors         51442 Hydraulic Sewage Cleaner	51201 Snow Plow	51203 Snow Blade				
51301 Anvil         51310 Backhoe         51319 Planner Used for Lumber           51303 Crane         51311 Transit         51321 Excavator           51304 Earthmover         51312 Bulldozer         51322 Warning Signs           51305 Fork Lift         51313 Other Equip Attachment         51323 Pay Loader           51306 Front End Loader         51314 Cement Equipment         51324 Stump Cutters           51307 Post Hole Digger         51315 Distance Measure         51399 MiscConstruct/Engineer           51308 Scaffold         51317 Plotter Stereo           51309 Tractor         51318 Trencher           514 BUILDING AND PLANT           51401 Alarm System         51411 Emergency Lights         51424 De-Aerator           51402 Central Air Conditioner         51412 Boiler         51425 Water Softener           51404 Fork Lift         51413 Air Compressor         51431 Ventilation Systems           51405 Furnace         51416 Water Pump         51432 Regulator           51406 Generator         51417 Air Lift         51438 Chemical Tank           51407 Pump         51420 Sewage Grinder         51439 Shelving           51409 Transformer         51421 Conveyors         51442 Hydraulic Sewage Cleaner	51202 Snow Blowers	51299 Misc Snow Plow/Equip				
51303 Crane51311 Transit51321 Excavator51304 Earthmover51312 Bulldozer51322 Warning Signs51305 Fork Lift51313 Other Equip Attachment51323 Pay Loader51306 Front End Loader51314 Cement Equipment51324 Stump Cutters51307 Post Hole Digger51315 Distance Measure51399 MiscConstruct/Engineer51308 Scaffold51317 Plotter Stereo51309 Tractor51318 Trencher51401 Alarm System51411 Emergency Lights51424 De-Aerator51402 Central Air Conditioner51412 Boiler51425 Water Softener51404 Fork Lift51413 Air Compressor51431 Ventilation Systems51405 Furnace51416 Water Pump51432 Regulator51406 Generator51417 Air Lift51438 Chemical Tank51407 Pump51420 Sewage Grinder51439 Shelving51409 Transformer51421 Conveyors51442 Hydraulic Sewage Cleaner	513 CC	DNSTRUCTION AND ENGINEERING EQ	UIPMENT			
51304 Earthmover51312 Bulldozer51322 Warning Signs51305 Fork Lift51313 Other Equip Attachment51323 Pay Loader51306 Front End Loader51314 Cement Equipment51324 Stump Cutters51307 Post Hole Digger51315 Distance Measure51399 MiscConstruct/Engineer51308 Scaffold51317 Plotter Stereo51309 Tractor51318 Trencher51401 Alarm System51411 Emergency Lights51424 De-Aerator51402 Central Air Conditioner51412 Boiler51425 Water Softener51404 Fork Lift51413 Air Compressor51431 Ventilation Systems51405 Furnace51416 Water Pump51432 Regulator51406 Generator51417 Air Lift51438 Chemical Tank51407 Pump51420 Sewage Grinder51439 Shelving51409 Transformer51421 Conveyors51442 Hydraulic Sewage Cleaner	51301 Anvil	51310 Backhoe	51319 Planner Used for Lumber			
51305 Fork Lift51313 Other Equip Attachment51323 Pay Loader51306 Front End Loader51314 Cement Equipment51324 Stump Cutters51307 Post Hole Digger51315 Distance Measure51399 MiscConstruct/Engineer51308 Scaffold51317 Plotter Stereo51309 Tractor51318 Trencher514 BUILDING AND PLANT51401 Alarm System51411 Emergency Lights51424 De-Aerator51402 Central Air Conditioner51412 Boiler51425 Water Softener51404 Fork Lift51413 Air Compressor51431 Ventilation Systems51405 Furnace51416 Water Pump51432 Regulator51406 Generator51417 Air Lift51438 Chemical Tank51407 Pump51420 Sewage Grinder51439 Shelving51409 Transformer51421 Conveyors51442 Hydraulic Sewage Cleaner	51303 Crane	51311 Transit	51321 Excavator			
51306 Front End Loader 51314 Cement Equipment 51324 Stump Cutters 51307 Post Hole Digger 51315 Distance Measure 51308 Scaffold 51317 Plotter Stereo 51309 Tractor 514 BUILDING AND PLANT 51401 Alarm System 51411 Emergency Lights 51424 De-Aerator 51402 Central Air Conditioner 51412 Boiler 51404 Fork Lift 51413 Air Compressor 51431 Ventilation Systems 51405 Furnace 51416 Water Pump 51432 Regulator 51406 Generator 51420 Sewage Grinder 51409 Transformer 51421 Conveyors 51442 Hydraulic Sewage Cleaner	51304 Earthmover	51312 Bulldozer	51322 Warning Signs			
51307 Post Hole Digger51315 Distance Measure51399 MiscConstruct/Engineer51308 Scaffold51317 Plotter Stereo51309 Tractor51318 Trencher514 BUILDING AND PLANT51401 Alarm System51411 Emergency Lights51424 De-Aerator51402 Central Air Conditioner51412 Boiler51425 Water Softener51404 Fork Lift51413 Air Compressor51431 Ventilation Systems51405 Furnace51416 Water Pump51432 Regulator51406 Generator51417 Air Lift51438 Chemical Tank51407 Pump51420 Sewage Grinder51439 Shelving51409 Transformer51421 Conveyors51442 Hydraulic Sewage Cleaner	51305 Fork Lift	51313 Other Equip Attachment	51323 Pay Loader			
51308 Scaffold51317 Plotter Stereo51309 Tractor51318 Trencher514 BUILDING AND PLANT51401 Alarm System51411 Emergency Lights51424 De-Aerator51402 Central Air Conditioner51412 Boiler51425 Water Softener51404 Fork Lift51413 Air Compressor51431 Ventilation Systems51405 Furnace51416 Water Pump51432 Regulator51406 Generator51417 Air Lift51438 Chemical Tank51407 Pump51420 Sewage Grinder51439 Shelving51409 Transformer51421 Conveyors51442 Hydraulic Sewage Cleaner	51306 Front End Loader	51314 Cement Equipment	51324 Stump Cutters			
51309 Tractor51318 Trencher514 BUILDING AND PLANT51401 Alarm System51411 Emergency Lights51424 De-Aerator51402 Central Air Conditioner51412 Boiler51425 Water Softener51404 Fork Lift51413 Air Compressor51431 Ventilation Systems51405 Furnace51416 Water Pump51432 Regulator51406 Generator51417 Air Lift51438 Chemical Tank51407 Pump51420 Sewage Grinder51439 Shelving51409 Transformer51421 Conveyors51442 Hydraulic Sewage Cleaner	51307 Post Hole Digger	51315 Distance Measure	51399 MiscConstruct/Engineer			
514 BUILDING AND PLANT51401 Alarm System51411 Emergency Lights51424 De-Aerator51402 Central Air Conditioner51412 Boiler51425 Water Softener51404 Fork Lift51413 Air Compressor51431 Ventilation Systems51405 Furnace51416 Water Pump51432 Regulator51406 Generator51417 Air Lift51438 Chemical Tank51407 Pump51420 Sewage Grinder51439 Shelving51409 Transformer51421 Conveyors51442 Hydraulic Sewage Cleaner	51308 Scaffold	51317 Plotter Stereo				
51401 Alarm System51411 Emergency Lights51424 De-Aerator51402 Central Air Conditioner51412 Boiler51425 Water Softener51404 Fork Lift51413 Air Compressor51431 Ventilation Systems51405 Furnace51416 Water Pump51432 Regulator51406 Generator51417 Air Lift51438 Chemical Tank51407 Pump51420 Sewage Grinder51439 Shelving51409 Transformer51421 Conveyors51442 Hydraulic Sewage Cleaner	51309 Tractor	51318 Trencher				
51402 Central Air Conditioner51412 Boiler51425 Water Softener51404 Fork Lift51413 Air Compressor51431 Ventilation Systems51405 Furnace51416 Water Pump51432 Regulator51406 Generator51417 Air Lift51438 Chemical Tank51407 Pump51420 Sewage Grinder51439 Shelving51409 Transformer51421 Conveyors51442 Hydraulic Sewage Cleaner	514 BUILDING AND PLANT					
51404 Fork Lift51413 Air Compressor51431 Ventilation Systems51405 Furnace51416 Water Pump51432 Regulator51406 Generator51417 Air Lift51438 Chemical Tank51407 Pump51420 Sewage Grinder51439 Shelving51409 Transformer51421 Conveyors51442 Hydraulic Sewage Cleaner	51401 Alarm System	51411 Emergency Lights	51424 De-Aerator			
51405 Furnace51416 Water Pump51432 Regulator51406 Generator51417 Air Lift51438 Chemical Tank51407 Pump51420 Sewage Grinder51439 Shelving51409 Transformer51421 Conveyors51442 Hydraulic Sewage Cleaner	51402 Central Air Conditioner	51412 Boiler	51425 Water Softener			
51406 Generator51417 Air Lift51438 Chemical Tank51407 Pump51420 Sewage Grinder51439 Shelving51409 Transformer51421 Conveyors51442 Hydraulic Sewage Cleaner	51404 Fork Lift	51413 Air Compressor	51431 Ventilation Systems			
51407 Pump51420 Sewage Grinder51439 Shelving51409 Transformer51421 Conveyors51442 Hydraulic Sewage Cleaner	51405 Furnace	51416 Water Pump	51432 Regulator			
51409 Transformer 51421 Conveyors 51442 Hydraulic Sewage Cleaner	51406 Generator	51417 Air Lift	51438 Chemical Tank			
	51407 Pump	51420 Sewage Grinder	51439 Shelving			
51410 Water cooler 51422 Water Heater 51499 Miscellaneous	51409 Transformer	51421 Conveyors	51442 Hydraulic Sewage Cleaner			
	51410 Water cooler	51422 Water Heater	51499 Miscellaneous			

508 MED/ HEAVY TRUCK/TRLRS

515 MANUFACTURING EQUIPMENT					
51503 Saw Mill	51517 Tailoring Equipment Sewing	51524 Food Processing Equip			
51512 Furniture Equipment	51518 Highway Sign Equipment	51599 Miscellaneous			
51513 Sealer Machine	51519 Soap Making Equipment				
51516 License Plates	51521 Print Shop Equipment				
516 DES	IGN AND LOCATION ENGINEERING EC	QUIPMENT			
51601 Drafting Equipment	51602 Blueprint Machine	51603 Survey			
5	17 ENGINEERING TESTING EQUIPME	NT			
51701 Geology Equipment	51708 Augur	51710 Safety/Hazard Test Equip			
51707 Equipment Cleaner	51709 Specialized Equipment				
5	18 PAVING MAINTENANCE EQUIPME	NT			
51801 Roller	51804 Paver, Bit	51808 Pavement Test Equipment			
51802 Sweeper	51805 Jackhammer	51809 Road Crk/Joint Seal Mach			
51803 Tar Pot	51806 Mud Jack	51810 Line Marker			
	520 Traffic Counters				
52001 Traffic Counter	52003 Detector (Traffic)	52005 Recorder			
521	MEDICAL AND LABORATORY EQUIP	MENT			
52101 Centrifuge	52128 Distillery Still	52157 Geiger Counter			
52102 Microscope	52129 Pharmacy Equipment	52163 Field and Test			
52104 Hospital Bed	52130 Scales	52164 Biological			
52105 Wheelchair	52131 Optical Equipment	52174 Biochemistry Lab Equip			
52116 Oxygen Equipment	52132 Table (Exam)	52175 Clinical Lab Equipment			
52117 X ray Equipment	52133 Electroencephalograph	52176 Speech/Hearing Equip			
52119 Autoclave	52134 Sterilizer	52180 Ultra Violet Light			
52120 EKG Machine	52135 Blood Test Equipment	52194 Dressing/Utility Cart			
52121 Chromatograph	52136 Therapy Equipment	52195 Medical Locker			
52122 Spectrophotometer Equip	52137 Dental Equipment	52196 Thermometer			
52124 Incubator	52156 Meters	52197 Defibrillator Monitor			
		52199 Miscellaneous			
522 EDUCATIONAL EQUIPMENT					
52202 Projector	52213 Video Equipment	52231 Engraver			
52203 Chalk-Board	52214 Slide Set	52236 Vocational Equipment			
	52216 Films	52237 Teaching Machine			
52204 Braille Writer					
52204 Braille Writer 52205 Tape Recorder	52217 Electronic Trainers	52239 Transmitter - Mike			
	52217 Electronic Trainers 52218 Binoculars	52239 Transmitter - Mike 52241 Display Case			
52205 Tape Recorder					

**ENTAP Training** 

523 RECREATIONAL EQUIPMENT				
52303 Playground equipment	52311 Basketball Goal	52325 Weight machine		
52305 TV	52312 Musical Instruments	52338 VCR		
52306 Record Player – Stereo	52317 Venetian Blinds	52341 TV/VCR combo		
52307 Pool Table	52319 Striking Bags	52399 Misc Recreational Equip		
	526 TRACTORS			
52600 Tractors	52602 Garden Tractor	52607 Mule		
52601 Farm Tractors	52606 Tractor Attachments			
	527 REST AREA EQUIPMENT			
52701 Display Cases	52702 Office Furniture	52704 Vending Machines		
	528 AIRCRAFT			
52801 Aircraft	52802 Aircraft Engines			
	529 SPREADERS			
52901 Spreader				
	530 RADIO EQUIPMENT			
53001 CB Radio	53012 Short Wave Equipment	53217 Bagger		
53003 Radar Speed & Distance	53013 Frequency Counter	53022 Auto Call Dist. Equip		
53005 Consoles Base Station	53014 Oscilloscope	53025 Radio		
53006 Amplifier	53015 Power Supply	53027 Walkie Talkie		
53007 Converter	53016 Field Meter	53028 Pager		
53008 Scanner	53017 Monitor	53029 Radio Mobile Unit		
53009 Weather Monitor	53019 Camera Control Unit	53040 Misc Radio/Tele Equip		
53010 Battery Charger	53021 Telephone Equipment			
	531 WINDOW AIR CONDITIONER			
53101 Window Air Conditioner				
532 A	GRICULTURAL EQUIPMENT FOR FIELI	O CROPS		
53201 Bins	53208 Rake	53219 Wagon		
53202 Agricultural Disc	53210 Chemical Applicator	53222 Drill (Grain)		
53203 Harvester	53211 Cultivator	53223 Feed Mixer		
52305 Planter	53213 Shredder	53299 Misc Ag Equip Field Crops		
53206 Plow	53214 Sprayer			
53207 Pump	53216 Chopper			
	533 OTHER FARM EQUIPMENT			
53302 Roto Tiller	53306 Combine			
53303 Sod Cutter	53999 Misc.Farm Equipment			

534 BOATS, MOTORS AND OTHER MARINE				
53405 Inboard Motor	53409 Outboard Motors	53414 Row Boat - Wood		
53406 Marine Generator	53412 Row Boat - Fiberglass	53499 Misc Boat & Motor Equip		
53407 Other Boats	53413 Row Boat - Metal			
536 WEAF	PONS AND RELATED RIOT CONTROL I	EQUIPMENT		
53601 Pepper/Fogger	53609 Portable Target System	53699 Misc Safety/Police Equip		
52602 Revolver	53611 Handcuffs			
53607 Metal Detector	53614 X-Ray Security System			
	537 WEIGH STATION EQUIPMENT			
53701 Scales				
	538 LANDSCAPING EQUIPMENT			
53802 Lg. Landscaping Equipment				
	539 SHOP EQUIPMENT			
53902 Buffer Polisher	53924 Tire Changer	53962 Roto Rooter Marpack		
53903 Drill	53928 Air Cleaner	53964 Wheel Aligner		
53904 Drill Press	53929 Paint Sprayer	53968 Die and Tap Set		
53905 Hydraulic Jack or Lift	53930 Tool Chest	53969 Tank (Below Ground)		
53906 Lathe – Metal	53931 Engine Analyzer	53970 Gas Pumps		
53908 Metal Detector	53934 Ladder – All types	53971 Tank (Above Ground)		
53909 Misc Testing Equipment	53937 Chain Hoist	53972 Air Operated Tools		
53911 Sander	53938 Lube Gun	53976 Hydraulic Press		
53913 Saws, Power	53942 Freight Dolly	53979 Pallet Truck		
53915 Welder	53946 Fork Lift	53980 Metal Shears		
53916 Electric Shears	53948 Wheel Balancer (tire)	53982 Misc. Tools		
53918 Sewer Auger	53949 Key Making Machine	53994 Heat Gun		
53920 High Pressure Water Clnr	53950 Blower	53997 Milling Machine for Metal		
53921 Grinder	53952 LP Gas Tanks	53999 Misc Shop Equipment		
53922 Battery Charger	53953 Hydraulic Bender			
53923 Wrench Torque	53957 Generator			

Exclusively for use by the State of Indiana

Exclusively for use by the State of Indiana

Exclusively for use by the State of Indiana

Issue Date: 11/28/2007

Issue Date: 11/28/2007

ENTAP Training

**ENTAP Training** 

54002 Cassette Reader	54018 Multiplexor Board	54037 Reproducing Equipment
54003 Central Processing Unit	54020 Controller 657	54044 Micro Computer
54004 Disk	54021 Memory	54045 Data Line Tester
54005 Disk Drive	54022 Switching Unit	54046 Battery Back up
54007 Key Punch/Card Punch	54024 Teletype Terminal	54047 Communication Controller
54008 Key Verifier	54027 Console	54048 Ethernet System
54009 Printer	54028 Power Dist. Unit	54049 Backup System
54010 Print Controller	54029 Multi Communications Unit	54050 Terminal Server
54012 Tape Controller	54030 Card Reader	54051 Network Equipment
54013 Tape Drive	54031 Card Reader Punch Unit	54055 Midrange I/O Device
54014 Data Terminal	54032 Modem	54099 Misc Mainframe Equip
54015 Module Video Support	54034 Mini Computer	
54017 Controller 658	54036 Sorter	
54101 35mm SLR	54109 Projector	54117 Lens
54102 35mm Other	54111 Video Equipment	54118 Movie Camera
54103 Developing Tank	54114 ID Camera	54119 Visual Equipment
54105 Microfilm Camera	54115 Camera	54199 Misc Camera Equipment
54108 Polaroid Camera	54116 Photo Enlarger	
54204 Oxygen Tank	54217 Sound Level Meter	
54210 Fire Control System	54299 Misc. Fire Fighting Equip	
	543 TRASH DUMPSTER	
54301 84 GMC Bridadier Comm		
544 MICRO	FORM, READER AND REPRODUCING	EQUIPMENT
54401 Reader	54402 Reader/Printer	54406 Camera
	553 SOFTWARE	
55303 Software-mainframe Apps	55325 Software Storage	55335 Software-Midrange Ops
55305 Software-mainframe Ops	55334 Software-Midrange Apps	
55401 PC System Unit	55408 PC Plotter	55418 PC External Disk Drive
55402 PC Keyboard	55409 PC Internal Upgrade	55419 CPU Unit
55403 Laptop/notebook	55411 PC Internal DiskDrive	55420 External Expansion Unit
55404 PC Monitor	55413 PC Memory Expansion Bd	55422 Other PC Equip
55405 PC Printer	55415 PC Modem – External	55450 Storage Server
55406 PC DotMatrix Printer	55416 PC Peripherals	55451 Storage Server – I/O Dev
55407 PC Laser Printer	55417 PCConn Overhead Disp	

540 MAIN FRAME COMPUTERS AND PERIPHERAL DEVICES

601-609 INDOT INFRASTRUCTURE USING MODIFIED APPROACH					
60100 Interstate Roads	60100 Interstate Roads 60400 Interstate Bridges 60700 St Institution/Prop Roads				
60200 NHS Roads 60500 NHS Bridges Non Interstate		60800 St Institution/Prop Bridges			
60300 Non NHS Roads	60600 Non NHS Bridges	60900 Work in Progress			
614-617 DNR INFRASTRUCTURE USING DEPRECIATION APPROACH					
61400 Dams	00 Dams 61601 Railroad Rehab 61602 Railroad Crossing				
61501 Railroad 61602 Railroad Signs and Equip 61701 Ports Commission Sts.					

## AMT02


**ENTAP Training** 

**ENTAP Training** 

# **Adding Assets Using Express Add**

The State of Indiana requires that Assets be acquired through the procurement applications. Therefore, the only time that assets will be added through the Asset Management module would be when assets have been donated to the State, or for data entry in order to reconcile back to the Agency's financial books (General Ledger).

This diagram depicts the steps involved in adding an asset using the Express Add component:



#### AMD06

How assets are entered will be determined by the asset entry workflow. Perhaps assets are entered when the financial paperwork has been received. In this case, Express Add may the proper choice to add the asset. This option enables the asset to be entered with detailed cost information and little or no physical information. Depreciation can begin to accrue as soon as the asset has been added. Later on physical information can be added in Basic Add that is needed to properly track the asset.

Adding assets using Express Add is quick and efficient:

- Express Add enables you to add owned assets quickly and
- Assets added with Express Add are capitalized automatically, and most of the information in the pages can be defaulted from an asset profile.

## **Additional Notes**

The Express Add component is comprised of three pages:

- Cost/Asset Information page
- Depreciation Information page
- Tax Information page the State has NO Tax considerations.

Express Add also enables you to enter accumulated depreciation for assets. Use the Cost/Asset Information page to enter information about how an asset will be capitalized.


Exclusively for use by the State of Indiana **ENTAP Training** Issue Date: 11/28/2007

#### **How to Get There**

Use this Use this page to add assets using Express Add:

# **Navigation**

Asset Management >> Owned Assets >> Express Add >> Cost/Asset Information



#### AMSC23

Cost/Asset Information page

Once you save this page, you cannot continue to add or change information in this component. You must go to the Asset Cost Adjust/Transfer page or the Asset Basic Information pages to make non-financial changes.

# NOTE

PeopleSoft Express Add has been configured so that assets with values over \$500 all require a Tag Number, Location and Custodian. PeopleSoft will accept transactions missing any combination of the three required fields for potential assets costing less than the \$500 threshold.

# **Completing the Cost/Asset Information page**

Select a *Profile ID* to use a profile defined in the Asset Profile. The current asset will default all financial depreciation information defined in that profile.

All assets for the State of Indiana require that *Tag Number* be populated. Each Agency is required to come up with a determination of how this is to be done.

Typically, the *Transaction Date* represents the date you actually acquired the asset and the *Accounting Date* represents the date you want this transaction posted to your general ledger.

*Transaction Date* needs to be changed when there is an error in the Acquired Date. Do NOT change the *Accounting Date*.

JOTE

The Accounting Date must be the same or later than the Transaction Date. For capitalized assets, keep in mind that any difference between Accounting and Transaction dates will affect depreciation as well as posting.

Step	Action
1	Assign costs to <i>Department</i> and <i>Project ID</i> Chartfields and to an asset <i>Category</i> by selecting the appropriate values. Use <i>Cost Type</i> to break down portions of the asset cost and enter as many cost types as needed for each transaction.
2	Salvage Value is calculated based on the selections for it at the asset profile level.
3	Enter the Acquisition Date for the asset. Enter an Acquisition Code, which indicates how you acquired the asset. The default is purchased.
4	If this is a group asset, select the <i>Group Asset Flag</i> option that applies: Group Asset or Group Member. The default is None.
5	The Capitalized Asset check box defaults from the asset profile.

#### AMT03

ENTAP Training

Exclusively for use by the State of Indiana
Issue Date: 11/28/2007

Exclusively for use by the State of Indiana
Issue Date: 11/28/2007


ENTAP Training

#### **How to Get There**

Use this page to enter depreciation information for your asset:

# **Navigation**

Asset Management >> Owned Assets >> Express Add >> Depreciation Information



AMSC24

Depreciation Information page

# Completing the Express Add – Depreciation Information page

The *In Service Date* is the date the asset was made available for use. This date plus the depreciation convention will determine when depreciation starts for this book. This date is reflected as the Begin *Depreciation Date*.

Select the Depreciate When In Service check box to allocate annual depreciation as of the date you placed the asset in service. If you do not select this option, PeopleSoft Asset Management will allocate annual distribution as of the date determined by the depreciation convention. This option is valid only in the year the asset was acquired.



#### AMD07

Child Inherits Parent's Life checkbox. If you are working with parentchild component assets, all of the child assets will have their own cost basis and depreciation attributes independent of the parent asset. If the child's asset life is different from that of the parent asset, you can specify that a new child asset of a parent component asset inherit the remaining life of the parent asset.

ENTAP Training

Exclusively for use by the State of Indiana
Issue Date: 11/28/2007

Exclusively for use by the State of Indiana
Issue Date: 11/28/2007

ENTAP Training

# Guided Activity | Adding Assets Using Express Add

# **Activity Overview**

In this activity, the student will add five assets that have been donated to them by the Orbeson Construction. President Roy Snodgrass has donated five various assets to the State of Indiana. These five assets will be added by using the Express Add component. These assets will be added to Agency/Business Unit 00050. Review the chart below before proceeding to the activity.

Profile ID	Description	Location	Tag Number (XXX= Agency)	Custodian	Cost
50501	2007 Chevy Malibu	IPSC0518	XXX1001	Bird,Larry	28,500.00
10101	Valparaiso Land	IPSC0518	XXX1002	Jordan,Michael	475,000.00
30124	Valparaiso Fish Hatchery	IPSC0518	XXX1003	Jordan,Michael	600,000.00
30107	Valpo Rest Area Building	IPSC0518	XXX1004	Jordan,Michael	1,500,000.00
50323	Wall Partition	IPSC0518	XXX1005	Bird,Larry	4,500.00

#### AMT04

Use the information in the following table to create the assets:

# **Exercise 1 - Adding Assets Using Express Add**

# Navigation -

Asset Management >> Financial Management >> Owned Assets >> Express Add

1 Enter the following information:

Page Element	Value or Status
Business Unit	00050
Asset Identification	NEXT

#### AMT05

2 Click *Add* and enter the following information:

Page Element	Value or Status	
Profile ID	50501	
Description	2007 Chevy Malibu	
Location	IPSC0518	
Tag Number	XXX1001	
Custodian	Bird,Larry	
Cost	28,500.00	

#### AMT06

3 Click the *Default Profile* button.

4	Click	Sa

Record Asset ID\_\_\_\_\_

Exclusively for use by the State of Indiana Issue Date: 11/28/2007

# Exercise 2 – Adding Asset using Express Add

1 Click *Add*. Enter the following information:

Page Element	Value or Status
Business Unit	00050
Asset Identification	NEXT

#### AMT07

2 Click *Add* and enter the following information.

Page Element	Value or Status
Profile ID	10101
Description	Valparaiso Land
Location	IPSC0518
Tag Number	XXX1002
Custodian	Jordan, Michael
Cost	475,000.00

## AMT08

- 3 Click the *Default Profile* button.
- 4 Click Save.

Record Asset ID\_\_\_\_\_

Exclusively for use by the State of Indiana

Issue Date: 11/28/2007

# Exercise 3 – Add Assets 3, 4 and 5

# Asset #3.

Page Element	Value or Status	
Business Unit	00050	
Asset ID	NEXT	
Profile ID	30124	
Description	Valparaiso Fish Hatchery	
Location	IPSC0518	
Tag Number	XXX1003	
Custodian	Jordan, Michael	
Cost	600,000.00	

#### AMT09

Record Asset ID\_\_\_\_\_

# Asset #4.

Page Element	Value or Status
Business Unit	00050
Asset ID	NEXT
Profile ID	30107
Description	Valparaiso Fish Hatchery
Location	IPSC0518
Tag Number	XXX1004
Custodian	Jordan,Michael
Cost	1,500,000.00

## AMT10

Record Asset ID\_\_\_\_\_

# Asset #5.


Page Element	Value or Status	
Business Unit	00050	
Asset ID	NEXT	
Profile ID	50323	
Description	Wall Partition	
Location	IPSC0518	
Tag Number	XXX1005	
Custodian	Bird,Larry	
Cost	4,500.00	

## AMT11

Exclusively for use by the State of Indiana Issue Date: 11/28/2007

# **Adding Assets Using Basic Add**

This diagram depicts the steps involved in adding an asset using the Basic Add component:



#### AMD08

Using Basic Add, the receiver can enter all the physical information for the asset as it is received. Later on cost information can be added using the Acquisition Detail page after the invoice has been received.

Basic Add (also known as Asset Basic Information) is another way to add assets. It is the standard method for adding assets.


The Basic Add component is comprised of multiple pages that enable the asset user to enter and adjust both capital and non-capital assets with the maximum amount of both financial and physical detail.

#### **How to Get There**

Use the Asset Information 1 page to add basic information manually, or add to or change information entered earlier:

# **Navigation**

Asset Management >> Owned Assets >> Basic Add >> Asset Information1



#### AMSC25

Asset Information 1 page

Enter the *Tag Number* assigned to the asset. This automatically selects the Taggable Asset option. PeopleSoft Asset Management performs physical inventory using the asset's tag number.

Step	Action
1	The Acquisition Date is the date you actually acquired the asset. This field is used for informational purposes only.
2	<ul> <li>The Acquisition Code indicates how you acquired the asset. Select one of the following options:</li> <li>Constructed – Use for constructed assets</li> <li>Donated – Use for donated assets</li> <li>Leased – All leased assets must be entered through the ePro process.</li> <li>Purchased – Used for purchased assets. This is the default.</li> <li>Trade In – This option is not valid for this page. You must add Trade Ins on the Asset Express Add page.</li> <li>Transferred – Transferred either within the same business unit or to another business unit.</li> </ul>
3	The Capitalized Asset box will be selected (display only) if this asset has been capitalized.
4	Select the appropriate box to indicate whether this asset is a <i>New Asset</i> or a <i>Replacement Asset</i> and select a Replaced Asset ID if appropriate.
5	Select Asset is Available if appropriate. Fields will appear where you can enter a Contact name and Phone #.
6	If this is a parent or child asset, select the appropriate option in <i>Parent/Child</i> . If this is a child asset, enter the Parent Asset ID it should be associated with. The default is None. Parent/Child assets cannot also be composite or group assets.


## AMT12

## **How to Get There**

Use the Asset Information 2 page to add basic information manually, or add to or change information entered earlier:

# **Navigation**

Asset Management >> Owned Assets >> Basic Add >> Asset Information 2



#### AMSC26

Asset Information 2 page

This is a custom page created for the State of Indiana.

The State of Indiana requests that the Agencies record details in the Manufacturer Information section of the Asset Information2 page.

Serial Number: Manufacturer's number provided directly on asset. This will be most helpful when managing issues on the asset with the manufacturer.

Exclusively for use by the State of Indiana Exclusively for use by the State of Indiana **ENTAP Training ENTAP Training** Issue Date: 11/28/2007 Issue Date: 11/28/2007

Mfg ID: This value represents the name of the manufacturer.

Model: Model name derived from the Manufacturer. For example General Motors creates Chevrolet's.


Version: Version of the Model. For example Chevrolet manufacturers Malibus.

Use the Asset Acquisition Details page to enter information about how your asset was acquired and to keep track of the separate costs and acquisition details of components that comprise an asset:

#### **How to Get There**

# **Navigation**

Asset Management >> Owned Assets >> Basic Add >> Asset Acquisition Detail



AMSC27

Asset Acquisition Detail page

Step	Action
1	Enter a <i>Description</i> of the component and the system that added it to PeopleSoft Asset Management in System Source. The <i>System Source</i> you enter must be valid in the PeopleSoft Financials and Distribution Source table.
2	Investment incentives come from PeopleSoft Projects. You can override amounts sent from Projects by entering them in <b>Incentive ID</b> . Enter <i>Quantity</i> of the asset and <i>Amount</i> of cost associated with this detail line, if applicable.
3	Enter the, Department, and Project ID you want associated with this acquisition detail line.

#### AMT13

# IOTE

As long as all your acquisition detail lines are for the same set of ChartFields (Project and Department) and for the same Category and Cost Type, you can enter them all at once and capitalize them later using the Capitalize button. However, if you are going to enter acquisition detail lines for more than one set of ChartFields and for more than one Category and Cost Type, you must enter and capitalize the acquisition detail lines for each set of ChartFields and for each Category and Cost Type separately.

Capitalize indicates whether this cost row has been capitalized. If it hasn't already been capitalized, you can assign it a status of To be Capitalized or Never Capitalize. Asset Management allows you to associate books with non-capitalized assets with the Never Capitalize status. Based on the option you choose, you will see either Capitalization Information or Non Capitalization Information on the page. Remember, all assets over \$500 need to be capitalized.

# OTE

You must enter all capitalized components, click Capitalize, and then click save before you add non-capitalized components to the same asset.

Step	Action
1	Use the Capitalization Information section to capitalize an asset using the book information stored in asset profiles, and enter cost information into those books.
2	Use the Non-Capitalization section to add non-capitalized costs associated with an asset on a book level.
3	The <i>Profile ID</i> identifies a profile set up in the Asset Profile table. The current asset will default to all financial and tax depreciation information defined in that profile. You must enter a profile ID for each asset you capitalize.
4	The <i>Transaction Date</i> and <i>Accounting Date</i> default to the current date or the dates specified as User Defaults. As a rule, you'll enter transactions in PeopleSoft Asset Management some time after they have occurred. The Transaction Date must be earlier than or equal to the Accounting Date. For capitalized assets, keep in mind that any difference between Accounting and Transaction dates will affect depreciation as well as posting.
5	The <i>Transaction Code</i> identifies which accounting entry template will be used for this asset. Only valid combinations of Asset Category, Transaction Code, Cost Type, and Transaction Type for which accounting entry templates exist will be accepted.
6	Asset Cost can be broken down by Department, Project ID, Category, Salvage Value, Quantity, and Cost Type. Only <i>Category</i> is a required field.

#### AMT14

Basic Add offers a place for you to keep a record of an asset's location; to store comments about it; and to record physical properties, such as color, height, weight, and to view a stored image of the asset.

# **How to Get There**

Use the Location/Comments/Attributes page to record the asset's location; enter comments about it; and enter physical properties, such as color, height, and weight; and to store an image of the asset.

# **Navigation**

Asset Management >> Owned Assets >> Basic Add >> Location/Comments/Attributes




AMSC28

Location/Comments/Attributes page (Location)

Step	Action
1	Select a <i>Location</i> . Locations are validated against the Location table and indicate the location as of the current effective dated row.
2	Enter the name or ID of any Document associated with the location.
3	You can also keep a record of the person authorizing the location by filling in the information in the Authorization section of the page.

#### AMT15



## AMSC29

Location/Comments/Attributes page (Physical and Custom Attributes)

Step	Action
1	Separate records marked by Date/Time, and Name of person making the comments can be maintained.
2	Physical Attributes: Enter or modify physical information about the asset, such as Color, Height, Width, Length, Weight, Capacity, and Power Rating.

#### AMT16

# **Asset Image**

To attach an image to an asset, the user will have to go into the windows client. Be careful in that images can take up a considerable amount of space. Currently the State of Indiana is NOT recommending the use of this functionality. If an Agency feels this is a feature that must be used, please conact AOS.

## **How to Get There**

Use this page to view an image of your asset:

# **Navigation**

Set Up Financials/Supply Chain >> Common Definitions >> File Locations and Images >> Image Location

T o attach an image, click on the magnify icon on the Asset Image page and then browse in folders for an image to attach in the image section of this component.



AMSC30

Exclusively for use by the State of Indiana

Issue Date: 11/28/2007

Exclusively for use by the State of Indiana

Exclusively for use by the State of Indiana

ENTAP Training

# Use the Asset Custodian/License/Manufacturer page to:


- Record custodial information
- Maintain information about the license or registration required to use this asset
- Keep track of information about the manufacturer.
- Maintain information about the location of your assets.

## **How to Get There**

Use this page to record custodial information, maintain license information, and keep track of information about and from the manufacturer:

# **Navigation**

Asset Management >> Asset Transactions >> Owned Assets, Basic Add >> Manufacturer/License/Custodian



#### AMSC31

Manufacturer/Licence/Custodian Page (Manufacturer)

## **Manufacturer Information:**

Use this section to keep track of information about and from the manufacturer.


Enter a Serial ID, Manufacturer Name, Model, Product Version, Production Date, Plant and Manufacturer Contact.

## **License Information**

Identify the agency or vendor issuing the license or registration. The *Agency ID* is validated against the Agency table, the Vendor ID against the Vendor table. Enter an Issue Date and an Expiration Date. Enter a Reg #. The Reg. Name identifies the person who was issued the license or registration.

Click the Address button to access the License Address page where you can enter address information associated with the asset's license.


Use the Comment field to enter notes you want to store with this information.



AMSC32

Manufacturer/License/Custodian page (License Information)

# **Custodian Information**



## AMSC33

Manufacturer/License/Custodian page (Custodian Information)

Step	Action
1	Select the <i>This Asset is Offsite</i> checkbox to indicate that the asset is not at your business location.
2	You can enter the name of the <i>Custodian</i> or skip to the <i>EmpIID</i> and enter the ID of an employee set up in the Employee Personal Data table.
3	You can track the use of the asset by <i>Department</i> and <i>Project ID</i> . These fields are for information only.
4	You can also keep a record of the person authorizing the custodian by filling in the Authorization information.

#### AMT17

**ENTAP Training** 

# **Adding Assets Using Basic Add**

# **Activity Overview**

The Kokomo Chrysler plant has had a tradition of donating one of its vehicles to the governor each year. This year the governor has chosen the 2007 Chrysler Crossfire. The car includes a state of the art stereo system and a pair of fuzzy dice.

Use the information in the following table to add the assets:

Description	Short Description	Equipment Class	Asset Status	Category	Profile
2007 Chrysler Crossfire	Crossfire	Equipment	In Service	505	50501
Stereo System	Stereo	Equipment	In Service	505	50501
Fuzzy Dice	Dice	Equipment	In Service	505	50501

## AMT18

Exclusively for use by the State of Indiana

Exclusively for use by the State of Indiana

Issue Date: 11/28/2007

Exclusively for use by the State of Indiana

Exclusively for use by the State of Indiana

ENTAP Training

# Guided Activity | Adding Assets Using Basic Add

# **Navigation**

Asset Management >> Financial Management >> Owned Assets >> Basic Add

- Click the Add a New Value tab.
- 2 On the Asset Basic Information page, enter the following information:

Page Element	Value or Status
Business Unit	00050
Asset Identification	NEXT

#### AMT19

Click *Add* and enter the following information:

Page Element	Value or Status
Description	2007 Chrysler Crossfire
Short Description	Crossfire
Tagable Asset	Select
Tag Number	(XXX)1006
Asset Class	50603 – Four Wheel Drive
Asset Type	Equipment
Asset Service	In Service
Acquisition Date	<current date=""></current>
Acquisition Code	Donated

#### AMT20

Access the Asset Acquisition Detail page and enter the following information.

Page Element	Value or Status
Description	2007 Chrysler Crossfire
System Source	AM Online Entry Panel
Quantity	1
Amount	36,000

## AMT21

Click the Acquisition Detail Chartfields link and enter the following information:

raye	lement	Value or Status
Depar	tment	001000 – Governors Office

#### AMT22

6 Click OK.

7 On the Asset Acquisition Detail page, enter the following information:

Page Element	Value or Status	
Category	505	
Profile ID	50501	
Capitalize	To be Capitalized	
Transaction Date	<current date=""></current>	
Accounting Date	<current date=""></current>	

#### AMT22

8 Click Capitalize.

9 Access the Location/Comments/Attributes page and enter the following information:

Page Element	Value or Status
Effective Date	<current date=""></current>
Location	022ISC1 – Indiana Supreme Court
Status	Authorized
Name	Letterman, David

## AMT23

Access the Manufacturer/License/Custodian page and enter the following information:

Page Element	Value or Status
Effective Date	<current date=""></current>
Custodian	Choose from the EmplID
EmplID	0004 – Donaldson, Linda

#### AMT24

- Click Save.
- Navigate out of the page.
- Select Asset Management, Financial Management, Owned Assets, Basic Add.
- Select the asset you just added.
- Click the *Add a New Row* button.
- 16 On the Asset Acquisition Detail page, enter the following information:

Page Element	Value or Status
Description	Stereo Equipment
System Source	AM Online Entry Panel
Quantity	1
Amount	1500.00
Capitalize	To be Capitalized

# AMT25

Click the Acquisition Detail Chartfields link and enter the following information:

Page Element		Value or Status
Department		001000 – Governors Office
AMT26	18 Cli	ick OK.

CHER OR

On the Asset Acquisition Detail page, enter the following information:

	Page Element	Value or Status
	Category	505
	Profile ID	50501
	Transaction Date	<current date=""></current>
	Accounting Date	<current date=""></current>

## AMT27

Access the Asset Acquisition Detail page

Click • to add a new row and enter the following information for the bagging stand:

Page Element	Value or Status	
Description	Fuzzy Dice	
System Source	AM Online Entry Panel	
Quantity	1	
Amount	50	
Capitalize	Never Capitalize	

#### AMT28

- Click Save.
- Click the Acquisition Detail ChartField link and enter the following information:

Page Element	Value or Status	
Department	001000 - Governors Office	

#### AMT29

- 24 Click OK to return to the Asset Acquisition Detail page.
- **25** Enter the following information:

Page Element	Value or Status
Category	505
Profile ID	50501
Transaction Date	<current date=""></current>
Accounting Date	<current date=""></current>

## AMT30

- **26** Click Non-Capitalize.
- 27 Click Save.

Record Asset ID\_\_\_\_\_

# **Copying Assets**

PeopleSoft Asset Management enables you to copy an existing asset.


Copying an asset can save you time if the existing asset's financial and physical information is similar to that of a new asset you want to create.

## **How to Get There**

Use this page to create an asset copy:

# **Navigation**

Asset Management >> Owned Assets >> Copy Existing Asset



#### AMSC34

**Create Asset Copies** 

NOTE

Child assets can be copied, but parent assets cannot be copied.

To copy an existing asset you need only change the financial and/or physical information that is different. Use this page to copy an existing asset if its financial and physical information is similar to that of a new asset you want to create. The system will automatically assign the new asset a different asset ID, or you can specify an asset ID

# **Using the Create Asset Copies page**

Step	Action
1	Enter new <i>Transaction</i> and <i>Accounting Dates</i> and a <i>Transaction Code</i> if needed. Transaction and Accounting Dates will default to the current date.
2	Asset Copy Options: The asset, book, cost, custodian, and location information is copied automatically. You can choose to copy all or some of the following additional asset information:  • Asset Acquisition Info  • Asset Comments
	Asset License/Registration Info
	Asset Non-Capitalized Cost Info
	Asset Attributes Info
	Asset Lease Info
	Asset Maintenance Info
	Asset Warranty Info
	<ul> <li>Enter a Description and Tag Number, and select Taggable Asset and enter a Serial ID if applicable for the new asset. These fields are not copied over from the original so that you can easily update them for each new asset. You have the option to change the Department, Project ID, Category, and Cost Type.</li> </ul>
	<ul> <li>Click Search to search for a parent Asset, if you are creating a child asset.</li> </ul>
	<ul> <li>Scroll to see the different books associated with the created assets.</li> </ul>
3	You have the option to change the Department, Product, Project ID, Category, and Cost Type.
4	Salvage Value is calculated based on the selections made at the asset profile level, either flat amount or percentage. Salvage Value is prorated based on a ChartField's cost if Flat Amount has been selected, and as a percentage of cost if Percentage has been selected.

#### AMT31

ENTAP Training

Exclusively for use by the State of Indiana

Exclusively for use by the State of Indiana

Exclusively for use by the State of Indiana

ENTAP Training

ENTAP Training

# **Guided Activity | Copying Assets**

In this activity, the student will add 15 additional Wall Partitions using the Copy Existing Asset feature.

# **Navigation**

Asset Management >> Financial Management >> Owned Assets >> Copy Existing Asset

- Click the Add a New Value tab.
- Enter the following information on the Copy Asset page:

Page Element	Value or Status
Business Unit	00050
Tag Number	XXX1005 – Wall Partition

#### AMT32

- On the Create Asset Copies page, enter 15 in the Num of Asset Copies to create field.
- 4 Click Create Assets.
- 5 Optional: Enter descriptions for each of the new assets.
- 6 Click Save.

# **Updating an Asset's Physical Attributes**


PeopleSoft Asset Management enables you to change information about how an asset was acquired, as well as the separate costs and acquisition details of components that comprise that asset.

#### **How to Get There**

The Basic Add component contains the pages used to update an asset's attributes. Use this page to add new physical information about your assets:

# **Navigation**

Asset Management >> Owned Assets >> Basic Add >> Asset Acquisition Detail



#### AMSC35

Asset Acquisition Detail page

Use the Insert Row 🕦 button to add a row, if needed, to enter any new physical information about your asset. This page is particularly useful if you are entering costs before they have been approved. The total capitalizable costs entered here are defaulted into the Capitalize Information section.

ENTAP Training

Exclusively for use by the State of Indiana

Exclusively for use by the State of Indiana

Issue Date: 11/28/2007

ENTAP Training

# Guided Activity | Updating an Asset's Physical Attributes

In this activity, you will review the activity overview and update information for an existing asset.

# **Activity Overview**

In this activity, you will add a Playground valued at 1,300 to the Valparaiso Rest Area Building for business unit 00050. The system source for this addition will be AM Online Entry Panel and the asset should be capitalized under the 301 category. Use the current date as the transaction date and accounting date.

# **Navigation**

Asset Management >> Financial Management >> Owned Assets >> Basic Add

- 1 Click the Add a New Value tab.
- 2 Enter 00050 as the Business Unit.
- Click *Search*, and select the Valparaiso Rest Area Building that you added earlier. You will need to select the Rest Area Building Tag Number with your initials.
- 4 Click the Asset Acquisition Detail link.
- 5 Click the Add a New Row button.
- 6 Enter the following information:

Page Element	Value or Status
Description	Playground
System Source	AM Online Entry Panel
Quantity	1
Amount	1,300.00

#### AMT32

- 7 Click OK to return to the Asset Detail page.
- 8 Enter the following information:

Page Element	Value or Status
Category	301
Capitalize	To be Capitalized
Transaction Date	<current date=""></current>
Accounting Date	<current date=""></current>

## AMT32

- 9 Click Capitalize.
- 10 Click Save.

ENTAP Training

Exclusively for use by the State of Indiana
Issue Date: 11/28/2007

Exclusively for use by the State of Indiana Issue Date: 11/28/2007

# **Using the Asset Search Utility**

PeopleSoft Asset Management provides a powerful search utility that enables you to search for an asset using numerous search criteria.

You can use any of the following criteria:

Business Unit	Serial ID	Parent ID	Category
Location	Group ID	Asset ID	Asset Status
Hazardous Asset	Tag Number	Profile ID	ChartFields
PO Unit	PO No.	Receipt Unit	Receipt No.
AP Unit	Voucher	Project Unit	Project ID


## AMT33

## **How to Get There**

Use the Search for an Asset page to search for an asset based on known criteria.

# **Navigation**

Asset Management >> Search for an Asset



Step	Action
1	Use the Go To>> link on the Search for an Asset page to quickly access other components in the system in order to transact against the asset you selected.
2	Use the Retrieve section to present your data with values that relate to one or more of the selections: Cost Information, Acquisition Information, Location, and/or Non Capital Assets.

## AMT34

# **Using the Asset Search Criteria page:**

Step	Action		
1	Use this portion of the page to establish your search criteria. You can select one specific attribute, such as Profile ID, or you can use a combination of known attributes, such as Profile ID, Business Unit, and the Purchasing Business Unit and Purchase Order associated with the asset's acquisition.		
2	Click Search to search for a Business unit, Asset Category, Location, Operating Unit, Department, Product, Parent ID, or Profile ID.		
3	If known, you can enter an Asset ID, Tag Number, Serial ID, Project, or Group ID. If known, you can select an Asset Status.		
4	To use asset acquisition information as part of your search criteria, enter a Purchasing Business Unit and/or Purchase Order, Receiving Business Unit and/or Receipt ID, Accounts Payable Business Unit and/or Voucher ID, or a Projects Business Unit and/or Project ID.		
5	The Retrieve section, added in 8.8, improves performance by retrieving only specific table data rather than all tables.		
6	Once you have chosen your search criteria, click Search. If you want to perform a new search, click Clear and enter new criteria.		
7	Search Results		
8	All assets that meet your search criteria will display on the lower portion of the page.		
9	Use the Sort By selections to order the list of assets. For a more sophisticated sort, click Advanced Sort to access the Advanced Sort page where you can select up to five criteria, and indicate whether they should be applied in ascending or descending order.		
10	Use this tab to view basic asset information, or use other tabs to view more detailed information including Asset Cost Information, Acquisition Details, and so on.		
11	Select the asset you want to work with  Use the Go To links to move to different components of PeopleSoft Asset  Management. The component you select will open populated with information about the selected asset. You can select from Asset Accounting Entries, Asset Basic		

#### AMT34

AMSC36 Search for an Asset page